


Plura View

Quick Guide




VR4more App

- Download VR4more 3.5.1 (Alpha) for Windows Platform
[Consensive VR4more](#)




VR4more App

- Download VR4more 3.5.1 (Alpha) for Windows Platform
[Consensive VR4more](#)
- Create shortcut for Side-By-Side Setup
 - Create shortcut for VR4more executable
 - Add `-popupwindow` to target path



VR4more App

- Download VR4more 3.5.1 (Alpha) for Windows Platform
[Consensive VR4more](#)
- Create shortcut for Side-By-Side Setup
 - Create shortcut for VR4more executable
 - Add `-popupwindow` to target path
- Start App via shortcut
 - At first start login with **PluraView** credentials
 - Further starts automatically login into the app



VR4more App

- Download VR4more 3.5.1 (Alpha) for Windows Platform
[Consensive VR4more](#)
- Create shortcut for Side-By-Side Setup
 - Create shortcut for VR4more executable
 - Add `-popupwindow` to target path
- Start App via shortcut
 - At first start login with **PluraView** credentials
 - Further starts automatically login into the app
- Close app: press **ALT + F4**

Configure PSTrack Client

- Set Client1 address to 127.0.0.1 and port 5000

The screenshot shows the PSTrack Client configuration window with the 'Interfacing' tab selected. The window has a menu bar (File, View, Help) and a tab bar (Tracking options, New device model, Edit device model, Multi-PST setup, Reference system, Interfacing, About).

VRPN:

- Server address: pstrack0@127.0.0.1:3883
- Enable Space Wand(s): ☐ Merge streams: ☐
- Connections: (empty list)
- Use custom configuration: ☐
- Configuration file: (empty field)
- Start button

DTrack:


- Client 1 address: 127.0.0.1 Port: 5000
- Client 2 address: (empty) Port: 5000
- Client 3 address: (empty) Port: 5000
- Multicast address: (empty) Port: 5000
- Output: ☒ Timestamp (ts), ☒ Devices (6d), ☐ 3D Points (3d), ☐ #Devices (6dcal)
- Start button

Logging:

- Output file: (empty field)
- Add Timestamp to file: ☐
- Log Relative Timestamp: ☐
- Output options: ☒ Devices, ☐ 3D Points
- Value separator: ;
- Decimal separator: .
- Frames to log: 0 (set to zero to log data until canceled)
- Start button

Configure PSTrack Client

- Set Client address to 127.0.0.1 and port 5000
- Glasses on ID 0
- (port and tracking target ID can also be adjusted in VR4more config)



Configure PSTrack Client

- Set Client1 address to 127.0.0.1 and port 5000
- Glasses on ID 0
- (port and tracking target ID can also be adjusted in VR4more config)
- Cardboard Marker placement for registration
 - marker edge at mirror frame center

